CSE 265: System and Network Administration

- The Network File System
 - NFS Introduction
 - Server-side NFS
 - Client-side NFS
 - NFS Statistics with nfsstat
 - Dedicated NFS File Servers
 - Automatic Mounting

NFS

- Network File System
- Allows systems to share filesystems among computers
- Originally designed to be transparent and stateless
- Consists of
 - A mounting protocol
 - Mount server
 - File service daemons
 - Diagnostic utilities



CSE 265: System and Network Administration

NFS

- Network File System
 - Version 2: slow
 - Originally released by Sun in 1985
 - Version 3: faster (common)
 - Version 4: security, locking (relatively new)
- Uses Sun's RPC (Remote Procedure Call) protocol (documented in RFC 1050, 1988)
 - Supports UDP or TCP for transport (v2,v3)
- File locking is worse under NFS v3 since servers are stateless

Magic cookies (NFS v2,v3)

- The server doesn't track which clients have mounted filesystems (stateless)
- Instead, the server discloses a secret/magic cookie that identifies the directory to the server on future access
 - Often the cookie is just the filesystem major and minor device IDs, plus directory inode
- Unmounting and remounting the actual filesystem on the server normally changes the cookie

Security and NFS

- Not originally designed for security!
- Access to NFS volumes is determined via /etc/exports
 - lists hostnames or IP addresses that have access
 - assumes clients will identify themselves correctly
- TCP wrappers/firewall can help protect service
- File-level access is managed according to UID, GID, and file permissions
 - Just as in local file systems

NFS Security Problems

- Users with given UID can access any file with that UID (even if different user)
 - Good reason for globally unique UID space!
- Root access on a client can access any file
- NFS typically uses option called "squashing root"
 - Makes incoming requests for UID 0 look like they came from some other user
 - Account named nobody is utilized
- Option all_squash does the same for all users

Server-side NFS

- Servers "export" a directory to make it available to others
- Servers run two daemons (v2,v3)
 - rpc.mountd to handle mount requests
 - rpc.nfsd for actual file service
- Filesystems to be exported are in /etc/exports

<pre># sample /etc/exports file</pre>				
/	<pre>master(rw) trusty(rw,no_root_squash)</pre>			
/projects	proj*.local.domain(rw)			
/usr	<pre>*.local.domain(ro) @trusted(rw)</pre>			
/home/joe	<pre>pc001(rw,all_squash,anonuid=150,anongid=100)</pre>			
/pub	<pre>(ro,insecure,all_squash)</pre>			

- Can modify and view exports using exportfs

Client-side NFS

- NFS filesystems are mounted much like local filesystems using **mount** hostname:directory
- Before mounting, filesystem must be exported
 - Check with **showmount** (v2,v3)

```
#showmount -e wume2
Export list for wume2:
/projects2 *.local.cse.lehigh.edu,davison
/projects1 *.local.cse.lehigh.edu,davison
```

- Use umount to unmount an NFS filesystem

- Can't be unmounted while in use
- Use **Isof** to find processes with open files

Mounting NFS filesystems

• Use mount for temporary mounts

mount -o rw,hard,intr,bg server:/home /home

/etc/fstab contains mounts for boot time

```
wume1:/home /home nfs \
intr,bg,rw 1 1
wume1:/var/spool/mail /var/spool/mail nfs \
intr,bg,rw 1 1
```

- Common options:
 - rw, ro, bg, hard, soft, intr, tcp, udp

NFS Statistics and Utilities

nfsstat

Server rpc	stats:			
calls	badcalls	badauth	badclnt	xdrcall
40996991	0	0	0	Θ
Server nfs	v3:			
null	getattr	setattr	lookup	access readlink
2 0%	428484 1%	25913 0%	444794 1%	398283 0% 3174 0%
read	write	create	mkdir	symlink mknod
10193400 24	1% 29048042	70% 69068	0% 695	0% 3110 0% 0 0%
remove	rmdir	rename	link	readdir readdirplus
5014 0%	81 0%	103716 0%	0 0%	38649 0% 1625 0%
fsstat	fsinfo	pathconf	commit	
853 0%	356 0%	0 0%	231730 0%	

netstat

• General network statistics, may help debugging

- showmount -a

• Shows all systems believed to have mounted filesystems

CSE 265: System and Network Administration

Dedicated NFS File Servers

- Dedicated NFS appliances are available
 - Network Appliance, EMC, HP/Dell, Oracle/Sun, etc.
 - Features
 - Provide Network Attached Storage (NAS)
 - Optimized for file service
 - Can scale to lots of storage and users
 - Often provide service to both Unix and Windows clients
 - More reliable
 - simpler software, redundant hardware, RAID
 - Easy to administer
 - Often provide backup and checkpoint facilities

Automatic Mounting

- Separate lines in /etc/fstab can be difficult in large networks
 - Maintaining /etc/fstab on more than a few dozen machines is tedious
 - Worse is when those machines mount from many hosts
- When an important host crashes, clients are crippled
 - Having a copy of the partition mountable elsewhere would be ideal
- An automounter mounts filesystems only when needed, and can work with replicated systems for redundancy

automount

- A background process that watches for requests for files within a specified directory
 - Uses autofs kernel-resident filesystem driver
 - Then mounts the requested filesystem
- /etc/init.d/autofs script is configured via /etc/auto.master

```
/misc /etc/auto.misc --timeout=300
```

 Each mount point has separate <u>map</u> file (or script), listing all valid subdirectories and how to get them

automount example

```
# This is an automounter map and it has the following format
# key [ -mount-options-separated-by-comma ] location
# Details may be found in the autofs(5) manpage
cd
               -fstype=iso9660,ro,nosuid,nodev :/dev/cdrom
                       -fstype=smbfs,rw,noexec,username=brian,pass\
brian-sun-windows
word=XYZ,uid=501,gid=501 ://gutenberg/brian
# the following entries are samples to pique your imagination
                                 ftp.example.org:/pub/linux
#linux -ro,soft,intr
            -fstype=ext2
#boot
                                :/dev/hda1
#floppy
             -fstype=auto
                                 :/dev/fd0
```

% mount
/dev/hda2 on / type ext3 (rw)
automount(pid7909) on /misc type autofs (rw,fd=5,pgrp=7909,minproto\
=2,maxproto=3)

% ps aux | grep automount root 7909 0.0 0.1 2644 620 pts/1 S 19:43 0:00 /usr/∖ sbin/automount --timeout 300 /misc file /etc/auto.misc